




Netelip

¡Hablar nunca ha sido tan barato!




Installing X-Lite

1. Run the X-Lite setup executable file. If you don't have it, you can download it from the next link:
http://www.netelip.com/software/X-Lite/X-Lite_Win32_1003I_30942.exe
2. Click 'Next' to begin the installation.



3. Read and accept the License Agreement. Click Next.






Netelip


¡Hablar nunca ha sido tan barato!



4. Select destination location. Click Next.



5. Select additional tasks, like where to add shortcut icons and if you want to launch the application when Windows starts. Click Next.






Netelip


¡Hablar nunca ha sido tan barato!



6. Now, you'll see the installation progress.



7. At the final step of the wizard, check the Launch X-Lite checkbox to start using the softphone.



8. Click Finish to complete the installation




Netelip

¡Hablar nunca ha sido tan barato!



Configuring X-Lite

1. Start X-Lite by using the Windows Start menu or by double-clicking the desktop icon. If it is already started you should see this icon  in the Taskbar. Click on it and the softphone will popup.
2. You should see the message "No SIP accounts are enabled"



3. To create the account: right click at the top of the softphone and choose SIP Account Settings.






Netelip


¡Hablar nunca ha sido tan barato!



4. The SIP accounts page is shown.



5. Click Add. The Properties of the new account will appear.





Netelip

¡Hablar nunca ha sido tan barato!



6. Under the Account tab, complete the fields within the User Details area, according to the details Netelip sent you via email. The required fields are:
 - a. Display Name:
 - b. User name: (User name)
 - c. Password: (Password)
 - d. Authorization user name: (User Name)
 - e. Domain: (Domain)

Example configuration:

User Name: 0123456789

Password: 12345

Domain: sip.netelip.com

Properties of Account1

Account | Voicemail | Topology | Presence | Advanced

User Details

Display Name: []

User name: 0123456789

Password: []

Authorization user name: 0123456789

Domain: sip.netelip.com

Domain Proxy

Register with domain and receive incoming calls

Send outbound via:

domain

proxy Address: []

target domain

Dialing plan: #1\|a\|a.T;match=1;prestrip=2;

OK Cancel Apply

7. For the remaining tabs, default settings are acceptable.



Netelip


¡Hablar nunca ha sido tan barato!




The last parameter to be configured is the codec.

1. Right click at the top of the softphone and choose Options.



2. Click on "Audio Codecs" from the "Advanced" tab. Make sure that the "G711 aLaw" codec is in the enabled codecs section. If it isn't, select it from the "Disabled codecs" section and click on . Click on OK and your softphone is ready to be used with the Netelip service.



3. The phone is ready to use!!.

Av. Juan López Peñalver, 21, Of. B26B - PTA - 29590 Campanillas - Málaga - Spain
Telefono: +34 902 02 12 70 Email: info@netelip.com Web: www.netelip.com